

C:\Program Files (x86)\NIBObeeLib\include\nibobee\analog.h

/* BSD-License:

Copyright (c) 2007 by Nils Springob, nicai-systems, Germany

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- * Neither the name nicai-systems nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

*/

```
/*! @file analog.h
 * @brief Zugriff auf die analogen EingÄnge.
 *        Die analogen EingÄnge und die Betriebsspannung werden automatisch gemessen,
 *        dazu mÃssen die globalen Interrupts aktiviert sein!
 * @author Nils Springob (nils@nicai-systems.de)
 * @date 2009-08-19
 */
```

```
#ifndef _NIBOBEE_ANALOG_H_
#define _NIBOBEE_ANALOG_H_
```

```
#ifdef __cplusplus
extern "C" {
#endif
```

```
enum {
    ANALOG_EXT0, //!< X1 Pin 1
    ANALOG_EXT1, //!< X1 Pin 2
    ANALOG_EXT2, //!< X2 Pin 1
    ANALOG_EXT3, //!< X3 Pin 1
    ANALOG_VOLT, //!< Versorgungsspannung
    ANALOG_L0, //!< linker Liniensor, IR-LED aus
    ANALOG_C0, //!< mittlerer Liniensor, IR-LED aus
    ANALOG_R0, //!< rechter Liniensor, IR-LED aus
    ANALOG_L1, //!< linker Liniensor, IR-LED ein
    ANALOG_C1, //!< mittlerer Liniensor, IR-LED ein
    ANALOG_R1, //!< rechter Liniensor, IR-LED ein
};
```

```
/*
 * Initialisierung des Liniensors.
 * Der AD-Wandler misst im Interruptmodus automatisch alle Werte, und schaltet
 * auch die IR-LEDs der Bodensensoren bei Bedarf ein und aus.
 * Die Interrupts mÃssen aktiviert sein, damit die Sensorwerte gemessen werden!
 */
void analog_init();
```

```
/*
 * Liefert den Wert des analogen Eingangs mit dem index @param idx zurÃck.
```

C:\Program Files (x86)\NIBObeeLib\include\nibobee\analog.h

```
* Die Interrupts mÃ¼ssen aktiviert sein, damit die Werte gemessen werden!
*/
uint16_t analog_getValue(uint8_t idx);

/*!
 * Diese Funktion wird nach einem kompletten Durchgang aller Sampling-KanÃ¤le aufgerufen
 */
void analog_irq_hook();

#ifndef __cplusplus
} // extern "C"
#endif

#endif // _NIBOSEE_ANALOG_H_
```